



How to Use the PLD Variables File

Countries: All

Solutions from SAP

SAP Business One 2007 A

June 2007 English





Contents

ntroduction	. 3
Getting the Layout Template Code	. 4
Use	. 4
Procedure	. 4
Norking with the PLD_Vars.xls File	. 5
Prerequisites	. 5
Use	. 5
Procedure	. 5
Copyrights & Trademarks	7



How to Use the PLD Variables File

Introduction

PLD users and layout designers are often at a loss when preparing a new layout or trying to modify an existing layout. This is because until now no information was provided as to the type of variables, their restrictions, and usage in a specific layout.

This How to Guide provides a simple scenario to help you understand the function of variables you may want to add. Use the information here instead of performing a trial-and-error process in layout customization.



This document is written with PLD_Vars.xls file version 2007 A, March 2007.



Getting the Layout Template Code


Use

The layout template code (Document ID) is your starting point for getting more information on this layout template.


Procedure

- 1. Open the required document or report, for example, Invoice.
- 2. Choose the icon on the tool bar.

The Layout Designer window opens displaying both the SAP Business One default print templates and the user-created templates.



- Select the template you want to edit and double-click it to open the Print Layout Designer.
- To get the template code, from the Print Layout Designer menu, select Display Document Properties.



Write down the Template Name and the first four characters that appear in the Document ID field on the General Tab.

The four characters stand for document type code and combine two elements:

- Document type For example, INV stands for Invoice.
- o Item type (2) or Service type (1)



Working with the PLD Vars.xls File


Prerequisites

You have a copy of the PLD Vars.xls file.

The PLD Vars.xls file contains detailed information on all the variables in all the system layout templates. You use this file to learn which variables are available for a specific layout and the restrictions on a specific variable.

Procedure

- 1. Open the PLD_Vars.xls file and choose the Vars sheet.
- 2. Do the following:
 - a. Filter the *TypeCode* column by the document type code.
 - b. Filter the Document Name column by the Template Name.
 - c. In the Local column, filter out your country code.




A list of variables relevant to this layout appears.

Column	Description
VARNUM	Displays the variable code.
Area Exclusive	If the area code is marked red, the area has special behavior described on the <i>Areas</i> tab. Some variables work properly only if they are nested within this particular area. You can check restrictions on this area on the <i>Vars Utilization</i> tab.
Metadata Type	Displays the variable type.




Description Displays a description of the variable.

- If you know the variable number beforehand, you can check its restrictions on the Vars Utilization sheet.
 - a. Choose the Vars Utilization sheet.
 - b. Filter the VARNUM column by the variable number.



The HANDLED ON column displays a restriction code on the specified variable.



The restriction description appears in the table above the columns.

- Red area codes the variable is exclusive to these areas.
- Green localization code the variable is exclusive to these localizations.
- Gray document types the variable is exclusive to these document types.

© SAP AG 2007 6



Copyrights & Trademarks

© Copyright 2007 SAP AG. All rights reserved.

The current version of the copyrights and trademarks at http://channel.sap.com/sbocustomer/documentation is valid for this document.